

Welcome to the HT Enthusiast Extended Workflow

v18.2.1

Workflow →
Description

↘ Introduction ↙
→ Prepare ←
↓ Calibrate ↑
← Analyze →



CalMAN HDR10



Featuring ...

- ▶ Home layout outlines the workflow structure with full access
- ▶ Comprehensive Notes Management - access button always at bottom right
- ▶ Integrated Session Setup layout with hardware configuration and dynamic range assessment, with access to Meter Profile Analysis, Meter Stability, and Screen Uniformity layouts
- ▶ Single layout takes all desired Pre- or Post-calibration readings
- ▶ Expanded Multi-Point Grayscale calibration, pre/post-cal charts, and datagrid layouts
- ▶ CMS Gamut detailed calibration layout
- ▶ Saturation Sweep detailed calibration, pre/post-cal charts, and datagrid layouts
- ▶ 3D Color Cube LUT calibration, detailed charts, and datagrid layouts
- ▶ Gamut Luminance & Color Check cal assessment, pre/post-cal charts and datagrid layouts
- ▶ High-count calibration points, HDR friendly with EOTF charts
- ▶ DeltaE is **ICtCp 720: Compensated** is default, **With Luminance Error** if indicated or after the "/"
- ▶ Layout indicators: **Calibration** **Charts** **# Datagrids**

Also featuring navigation for the Mouse Lazy ...

- ▶ Navigation bar on right shows where you are and takes you where you want to go
- ▶ Toggle buttons switch between complementary layouts with one click:
 - between the Calibration layouts and their corresponding Datagrid
 - between the Pre-Calibration Readings and Post-Calibration Readings
 - between corresponding Pre-Calibration and Post-Calibration Details
 - between corresponding Post-Calibration Details and Datagrids

And more!

INT

Intro

Next

HOME

Prepare

Session Setup

PreCal Read

Calibrate

↓ Gry

↓ CMS

↓ Sat

↓ LUT

↓ Lum

↓ CCK

PostCal Read

Analyze

↓ Gry

↓ Sat

↓ Lum

↓ CCK

↓ LUT

Final Check

Session Setup

PreCal Read

Notes

Next

Show Outline

WORKFLOW OVERVIEW

The HT Enthusiast Extended Workflow aims at providing all the possible calibration options in an accessible user-friendly manner.

The workflow is divided into four sections or zones with a corresponding color for the three working zones.

- 1) ► **Introduction:** Provides general information about the workflow and its features, and random access to all layouts
- 2) ► **Preparation Zone:** Enter session and device setup information, take pre-calibration readings for reference, plan the dynamic aspects of the session (contrast, brightness, etc.)
- 3) ► **Calibration Zone:** Contains the calibration layouts with matching datagrids, and the post-calibration readings layout for all views except the 2-Point Grayscale and 3D Color Cube LUT
- 4) ► **Analysis Zone:** Has detailed charts and datagrids for all views in the pre- and post-calibration states (except the 3D Color Cube LUT which feeds off the calibration layout) and a final check layout for dynamic range fine-tuning with a session summary

ACTIVE CALIBRATION VIEWS

- 2-Point Grayscale
- Multi-point Grayscale
- Saturation Sweeps, also used for basic CMS calibration
- Gamut Luminance
- Color Checker with option for Slim Datagrid
- 3D Color Cube LUT with tabs for Full-feature and Minimal
- Use Minimal layout tab where available for hopefully faster AutoCal.
- DeltaE is ICtCp 720, compensated by default, and with luminance error where indicated or after the "/".
- All active calibration layouts except 2-Point have full-screen datagrids.
- Use the Slim high-content Color Checker datagrid for faster processing of hundreds of colors.

ANALYSIS CHARTS

Except the 2-Point Grayscale and 3D Color Cube LUT, there are pre-calibration and post-calibration detail chart layouts for each active calibration view.

You can toggle between them by clicking the ↑PreCal or ↑PstCal button in the Nav Bar (they super-impose when the layout switches so just keep clicking to go back and forth). Other ↑ buttons in the Nav Bar perform similar toggling duties.

Unlike in the other color views, the CIE chart in the Color Checker pre- and post-calibration chart layouts is a display option accessible by checking the CIE Chart option.

Supplementing the charts are analysis datagrid layouts with both pre- and post-calibration data for each active calibration view. You can access them using the #Datagrid buttons.

KEY LAYOUTS

Home - has a layout map for getting the lay of the land and a fully loaded navigation matrix for access to all layouts.

Notes Management - Comprehensive notes management layout contains all notes for convenient editing, with access button at bottom right of all layouts.

Session Setup - Integrates calibration options, initial settings & notes, and hardware/device configuration.

Pre-Calibration Readings, Post-Calibration Readings - these identically configured layouts are master controls for the pre- and post-calibration states with combined and selective reading of all views. They feed all the detail charts and datagrids. You can toggle between the pre- and post-cal reading layouts, and between a reading layout and its corresponding detail layouts, in the Nav Bar (↑PreCal and ↑PstCal) and the explicit toolbar buttons.

Final Check - Analyzes and fine-tunes the dynamic range aspect and provides a comprehensive calibration summary.


NAVIGATION BAR

Displays the normal layout sequence with instant access across views and zones

Current Layout Context

Next / Back in workflow sequence and / or buttons for navigation to related layouts

Red arrow indicates position in workflow



Analysis Nav Bar and Next / Back buttons follow

current view:

Individual Pre-Cal or Post-Cal charts, or combined Pre- & Post-Cal Datagrids

Datagrids Pre-Cal & Post-Cal Charts → Analyze

Gry # Sat # Lum # CCK

Charts from Full & Minimal calibration → J LUT

Final Check

Layout indicators: ↑ Calibration J Charts # Datagrids

Navigation Bar → ←

✕ Show Outline

► Preparation (PRP)

- 1 ► Session Setup → Screen Uniformity → Meter Profile Analysis → Meter Stability
- 2 ► Pre-Calibration Readings

► Calibration (CAL)

- 4 ► 2-Point Grayscale Calibration
- 5 ► Multi-Pt Grayscale Calibration → Datagrid
- 6 ► CMS Gamut Calibration → Datagrid
- 7 ► Saturation Sweeps Calibration → Datagrid
- 8 ► 3D Color Cube LUT Calibration
- 9 ► Gamut Luminance Calibration Assessment → Datagrid
- 10 ► Color Checker Calibration Assessment → Datagrid (normal & slim versions)
- 11 ► Post-Calibration Readings

► Analysis (ANL)

- 11 ► Multi-Pt Grayscale Post-Cal Charts → Pre-Cal Charts → Datagrids
- 12 ► Saturation Sweeps Post-Cal Charts → Pre-Cal Charts → Datagrids
- 13 ► Gamut Luminance Post-Cal Charts → Pre-Cal Charts → Datagrids
- 14 ► Color Checker Post-Cal Charts → Pre-Cal Charts → Datagrids
- 15 ► 3D Color Cube LUT Calibration Detail Charts (from Full & Minimal calibrations)
- 16 ► Final Check + Summary – Fine Tune the Dynamic Range


NAVIGATION BAR

Displays the normal layout sequence with instant access across views and zones

Current Layout Context

Next / Back in workflow sequence and / or buttons for navigation to related layouts

Red arrow indicates position in workflow



Nav Bar Return

INT

Home

Back

Next

Intro

HOME

Prepare

Session Setup

PreCal Read

Calibrate

Multi-Point and 2-Point →

↓ Gry

↓ CMS

↓ Sat

Full & Minimal →

↓ LUT

↓ Lum

↓ CCK

PostCal Read

Analyze

↓ Gry

↓ Sat

↓ Lum

↓ CCK

Charts from Full & Minimal calibration →

↓ LUT

Final Check

Normal workflow sequence

Analysis Nav Bar and Next / Back buttons follow

current view:

Individual
Pre-Cal or
Post-Cal charts,
or combined
Pre- & Post-Cal
Datagrids

Datagrids Pre-Cal & Post-Cal Charts → Analyze

Gry

Sat

Lum

CCK

← context navigation →

Charts from Full & Minimal calibration →

↓ LUT

Navigation Bar → ←

7/26/2018 Calibration

 Home

Introduction

↗ Notes ↙

CalMAN 5

► Preparation

Start →

Session Setup

→

PreCal Read

StaUn • Meter Stability

StaUn • Screen Uniformity

PrflAn • Profile Analysis

↓ Analysis

← Back

Next →

Return

► Calibration

Grayscale

Gray ↕ 2-Pt Calibrate

Gray ↕ Mult-Pt Calibrate

CMS / Saturation Sweeps

CMS ↕ Calibrate

Satu ↕ Calibrate

3d Color Cube LUT

LUT ↕ Calibrate

↑ Has Full and Minimal layout tabs ↑

LUT Full # Cal Data

LUT Minimal # Cal Data

Gamut Luminance

Lumi ↕ Cal Assessment

Color Checker

CChk ↕ Cal Assessment

CChk # Cal Assessment Data

CcSlm # Slim Assessmnt Data

PostCal
Read

► Analysis

Grayscale

Gray # Pre/Post-Cal Data

Gray ∫ Pre-Cal Charts

Gray ∫ Post-Cal Charts

Saturation Sweeps / CMS

Satu # Pre/Post-Cal Data

Satu ∫ Pre-Cal Charts

Satu ∫ Post-Cal Charts

Gamut Luminance

Lumi # Pre/Post-Cal Data

Lumi ∫ Pre-Cal Charts

Lumi ∫ Post-Cal Charts

Color Checker

CChk # Pre/Post-Cal Data

CChk ∫ Pre-Cal Charts

CChk ∫ Post-Cal Charts

3d Color Cube LUT

LUT Full ∫ Cal Charts

LUT Minimal ∫ Cal Charts

Final
Check

↗ Notes ↙

Layout indicators:

↕ Calibration

∫ Charts

Datagrids

PreCal Read

↗ Notes ↙

← Back

Next →

Setup Notes

Calibration Notes

Return

Pre-Calibration Notes

REF
Notes

Calibration Description / Goals

Color Notes

Post-Calibration Notes

Return

Session Setup

10/29/2018 Calibration

(A) Session Options

Start New Session

Session Info

More Options

Use u'v' CIE Charts

Luminance Unit

cd/m²

Input Level

Video (16-235)

Stimulus Unit

Percent

DeltaE Formula

dE ICtCp 720

Colorspace Target

D65, HD BT.709

Gamma Formula

ITU BT.1886

Setup Notes

Calibration Description / Goals

Notes

Target Black and White

cd/m2 Blk

fl

cd/m2 Wht

fl

0.0001

3E-05

100

29.2

Target Gamma

1

(B) Display Settings

AV Mode

Cal Day 100 nits

Color Temp

Warm 2

Contrast

40

Sharpness

0

Brightness

1

Color

25

Backlight

20

Tint

0

TV Gamma

0

Cut

Gain

Red

-2

-4

Green

-4

-4

Blue

-2

-4

(C) Hardware Configuration

Meter

Find →

Kill All

Manage

Simulated Meter

Profile

Mode

Simulated

Pattern Source

Find →

Kill All

Manage

Source

Size

Constant APL 18

Delay

0.5

Display / Processor

Find →

Kill All

Manage

Lumagen Radiance 3D LUT

Radiance series 460800 baud COM4 with 3D LUT

DDC

Display Slot

CMS 0

Gray Levels

21

(D) Meter Setup

Position the meter as required for the projector or flat panel to insure accurate measurements when taking readings.

Projector

Flat Panel

(E) Dynamic Range

Select a suitable set of gray data points and check the gamma level across the full grayscale based on the current settings, and adjust the display's various level controls to get a suitable lowest and highest value, tweaking available Backlight, Brightness, Contrast and such, and optimize RGB fluctuations.

Select a clipping set of data points to check there is no clipping of the three primaries below and above the White level.

20 Point 5% Step 5-100%

RGB

DDC

Gamma

2.5

2.4

2.3

2.2

5

10

15

20

25

30

35

40

45

50

55

60

65

70

75

80

85

90

95

100

White / Black

100 / 0

Level

5

Gamma 0

2.4

CCT 0

6503

Y 0

0.0763

PRP Setup

Back

Next

HOME

Prepare

Calibrate

Analyze

Final Check

Session Setup

(A) Session Options

10/29/2018 Calibration

Start New Session

Session Info

More Options

Setup Notes

Calibration Description / Goals

Notes

Use u'v' CIE Charts

Luminance Unit

cd/m²

Input Level

Video (16-235)

Stimulus Unit

Percent

DeltaE Formula

dE ICtCp 720

Colorspace Target

D65, HD BT.709

Gamma Formula

ITU BT.1886

Display • 75Q9FN

cd/m2	Blk	fl	cd/m2	Wht	fl	Target Gamma
0.0001	3E-05		100	29.2		1

(B) Display Settings

AV Mode Cal Day 100 nits

Color Temp	Warm 2	Contrast	40	Cut	Gain
Sharpness	0	Brightness	1	Red	-2 -4
Color	25	Backlight	20	Green	-4 -4
Tint	0	TV Gamma	0	Blue	-2 -4

Display Controls

Input - Brightness 0

Input - Contrast 0

Input - Color 0


Input - Tint 0

Display Slot
CMS 0

Reset Display Slot

20 Point 5% Step 5-100%

RGB DDC



White / Black	cd/m ²
100 / 0	
Level	5
Gamma	0
CCT	0
Y	0
Target	2.4
	6503
	0.0763

PRP Setup

Back

Next

MtStb

MtPrf

HOME

Prepare

MtStb

MtPrf

PreCal Read

Calibrate

Gry

CMS

Sat

LUT

Lum

CCK

PostCal Read

Analyze

Final Check

Setup

Back

Next

Session Setup

7/26/2018 Calibration

(A) Session Options

Start New Session

Session Info

More Options

Setup Notes

Calibration Description / Goals

Notes

Display • 75Q9FN

cd/m2	Blk	fl	cd/m2	Wht	fl	Target Gamma
0.0001	3E-05		300	87.6		2.2

(B) Display Settings

AV Mode Cal Day 300 nits

Color Temp Warm 2

Contrast 41

Sharpness 0

Brightness 1

Cut Gain

Red 15 -4

Color 26

Backlight 29

Green 16 -1

Tint 15 / 0

TV Gamma 0

Blue 17 3

(C) Hardware Configuration

Meter Stability

Screen Uniformity

Profile Analysis

Create Profile

Meter Settings

Profile

Reference Meter Simulated Meter - 12345678

Advanced Options

Target Meter Simulated Meter - 12345678

Advanced Options

[Find more meters](#)

Source

Source - 1

Stimulus Level:

100

Prompt for pattern changes

Profile Information

Current Profile None

Add Profile

Display Type

	I	X	Y	Z
X	0	1	0	0
Y	0	0	1	0
Z	0	0	0	1

PRP
Setup

Back

Next

MtStb

PrflAn

HOME

Prepare

MtStb

PrflAn

PreCal
Read

Calibrate

I Gry

I CMS

I Sat

I LUT

I Lum

I CCK

PostCal
Read

Analyze

Final
Check

Setup

Notes

Back

Next



Setting Up the Session

[Return](#)

(A) CalMAN Session Options

Enter the session description & calibration options in the corresponding drop-downs and text boxes

- Click [Session Info] to enter additional information
- Click [More Options] to open the options panel - the red [X] can be used to close it
- Click the checkmark above/below [Big] to expand the note next to it

(B) Display Settings

Enter the initial display settings to use for the calibration in the corresponding boxes - you can provide alternates in the Pre- and Post-Calibration layouts

(C) Hardware Configuration

- To start calibrating your display/processor, first connect your meter.
 - Click the meter [Find] button and select your meter.
 - Select the Target Display Type.
- Connect to your reference pattern source generator.
 - Click the source [Find] button, and select your Source.
 - Select the pattern window size and resolution.
- Connect to your display/processor.
 - Click the display [Find] button and select your display or processor.
 - Click [DDC] to show the Direct Display Control panel when appropriate
- Click the corresponding [Configure] button for more options.
- Click on Profile to select, edit or create a meter profile.

(D) Meter Positioning

1a. For projectors position the meter facing the projection screen, far enough away from the screen to avoid reading the meter's own shadow (see illustration on the left). Continue to take readings.

1b. Press the read continuous button to take measurements of a white window while moving the meter up/down/left/right, until the Y Max reading is largest. When Y Max is highest, click *Stop*.

2. For flat panels position the meter on the center of the screen (see illustration on the right). You do not need to take readings for this placement.

3. You can also read the White level CCT based on the current settings - adjust the display's color temperature to best match the target CCT.

[Return](#)

(E) Dynamic Range

Overall Range

Adjust the Backlight control (for LED) to get the desired compromise between black and white levels: less Backlight = deeper black but lower white level, more Backlight = brighter white but higher black level too.

White Level

Data Points: select Clipping or Clipping with Peak White.

Adjust the Contrast to maximize the white level without clipping any of the three primaries.


Gamma Level

Data Points: select a full set of grayscale points for this.



Check the gamma level across the full grayscale based on the current settings, and adjust the display's gamma control to get a good match, tweaking with the Brightness for Black level & Contrast for White.

Meter Stability

Session Setup

CIE 1976 $u'v'$ 

dE ICtCp w/ Luminance Error



Clear History

Meter Profile Analysis



Manage Profiles

Clear Reference

Clear Profiled

CMS Gamut Analysis Target 100W → cd/m² 200 fL 58.37

Simulated Meter Read All as Reference Read All as Profiled



Select a meter and do the appropriate reference or profiled Read All or a Read Single selected color.
Select the same color in both CMS sliders to view a specific comparison: Reference is always on left or above.

Session Setup

Reference Meter CMS



	White	Red	Green	Blue	Cyan	Magenta	Yellow	100W
Y cd/m²	41.9106	9.0478	30.1955	3.0840	32.9133	12.0352	38.8511	80.9991
x: CIE31	0.3146	0.6329	0.2966	0.1495	0.2259	0.3176	0.4193	0.3145
y: CIE31	0.3300	0.3335	0.6016	0.0607	0.3275	0.1548	0.5044	0.3270
RED Linear 0-1	0.2127	0.2064	-0.0036	-0.0007	0.0030	0.2053	0.2100	0.4185
Green Linear 0-1	0.2089	0.0019	0.2122	0.0005	0.2080	0.0018	0.2091	0.4006
Blue Linear 0-1	0.2069	0.0004	0.0003	0.2109	0.2100	0.2113	0.0004	0.4083

Read Single as Reference →

Simulated Meter

Read Single as Profiled →

White

Red

Green

Blue

Cyan

Magenta

Yellow

100W

White

Red

Green

Blue

Cyan

Magenta

Yellow

100W


Profiled Meter CMS



	White	Red	Green	Blue	Cyan	Magenta	Yellow	100W
Y cd/m²	42.1935	8.9812	30.2228	3.1214	32.9342	12.0846	38.4611	81.6728
x: CIE31	0.3125	0.6363	0.2985	0.1514	0.2267	0.3192	0.4202	0.3107
y: CIE31	0.3314	0.3300	0.6002	0.0614	0.3291	0.1552	0.5021	0.3305
RED Linear 0-1	0.2073	0.2093	-0.0015	0.0009	0.0037	0.2079	0.2111	0.3955
Green Linear 0-1	0.2124	0.0005	0.2117	0.0003	0.2082	0.0014	0.2060	0.4123
Blue Linear 0-1	0.2077	0.0005	0.0003	0.2105	0.2077	0.2109	0.0012	0.4068

CMS Detail	Reference	Profiled	Ref Target
Red Linear	0.41851	0.39554	0.405
Green Linear	0.40064	0.41234	0.405
Blue Linear	0.40835	0.40679	0.405
Y cd/m²	80.999	81.673	80.999
x CIE31	0.31454	0.31072	0.31271
y CIE31	0.327	0.33045	0.32901
dE ICtCp	0.61 / 0.61	0.57 / 0.57	

Color Checker dE ICtCp Analysis



Read All as Reference Simulated Meter Read All as Profiled

PRP Profile

Setup

HOME

Prepare

Setup

Calibrate

Analyze

Profile

Create Profile

Meter Settings

Reference Meter

☐ Advanced Options

Target Meter

☐ Advanced Options

[Find more meters](#)

Source

Stimulus Level:

Select stimulus between 75 - 85 to avoid clipping and better sample the display

☐ Prompt for pattern changes

Profile Information

Current Profile

Display Type

	I	X	Y	Z
X	0	1	0	0
Y	0	0	1	0
Z	0	0	0	1

Select a meter and do the appropriate reference or profiled Read All or a Read Single selected color.
Select the same color in both CMS sliders to view a specific comparison: Reference is always on left or above.

Reference Meter CMS



	White	Red	Green	Blue	Cyan	Magenta	Yellow	100W
Y cd/m ²	41.9106	9.0478	30.1955	3.0840	32.9133	12.0352	38.8511	80.9991
x: CIE31	0.3146	0.6329	0.2966	0.1495	0.2259	0.3176	0.4193	0.3145
y: CIE31	0.3300	0.3335	0.6016	0.0607	0.3275	0.1548	0.5044	0.3270
RED Linear 0-1	0.2127	0.2064	-0.0036	-0.0007	0.0030	0.2053	0.2100	0.4185
Green Linear 0-1	0.2089	0.0019	0.2122	0.0005	0.2080	0.0018	0.2091	0.4006
Blue Linear 0-1	0.2069	0.0004	0.0003	0.2109	0.2100	0.2113	0.0004	0.4083


↑↓

Profiled Meter CMS



	White	Red	Green	Blue	Cyan	Magenta	Yellow	100W
Y cd/m ²	42.1935	8.9812	30.2228	3.1214	32.9342	12.0846	38.4611	81.6728
x: CIE31	0.3125	0.6363	0.2985	0.1514	0.2267	0.3192	0.4202	0.3107
y: CIE31	0.3314	0.3300	0.6002	0.0614	0.3291	0.1552	0.5021	0.3305
RED Linear 0-1	0.2073	0.2093	-0.0015	0.0009	0.0037	0.2079	0.2111	0.3955
Green Linear 0-1	0.2124	0.0005	0.2117	0.0003	0.2082	0.0014	0.2060	0.4123
Blue Linear 0-1	0.2077	0.0005	0.0003	0.2105	0.2077	0.2109	0.0012	0.4068

CMS Detail	Reference	Profiled	Ref Target
Red Linear	0.41851	0.39554	0.405
Green Linear	0.40064	0.41234	0.405
Blue Linear	0.40835	0.40679	0.405
Y cd/m ²	80.999	81.673	80.999
x CIE31	0.31454	0.31072	0.31271
y CIE31	0.327	0.33045	0.32901
dE ICtCp	0.61 / 0.61	0.57 / 0.57	




Screen Uniformity

Rows 3

Columns 3

Left to right

Session Setup



Gray Levels Only 4 Point 25% step 25-100%

Target Y 14.4603

Read 0

ΔE 0



Type Grayscale

PRP
ScUni

Setup

HOME

Prepare

Setup

Calibrate


Analyze

ScUni

Pre-Calibration Readings

7/26/2018 Calibration

Gamma Breakout Tot 2.86 Contrast 828

Black 0.097946 White 81.07 cd/m²

1 Grayscale Detail Charts 21 Point 5% step 0-100% Avg 0.32 / 9.01 Max 0.92 / 14.89




2 Saturation Sweeps

Detail Charts

25% Sweeps

Avg 0.51 / 10.02 Max 2 / 10.98



4 Color Checker


Detail Charts

3 Gamut Luminance

Detail Charts

4 Point 25% step 25-100%

Avg 0.95 / 8.18



Cal Day 300 nits

Pre-Cal Readings

Contrast
Brightness
BacklightTV Gamma
Color
TintRed Green Blue
Gain
Cut

Notes

Display Slot

CAL-DAY

Use [...] mid-screen or below to read all series or select one from the individual series above

Back

Next

2-Point Grayscale Calibration


Grayscale 2-Point Adjust

1. Reduce the Red, Green, and/or Blue (RGB) High controls to the lowest measured R, G, or B after the initial measurement of bright grayscale pattern. Continue doing this until you balance RGB to a deltaE of 3 or below (chart below).
2. Balance the RGB Low controls (if provided), while measuring a dark grayscale pattern.
3. Re-measure both bright grayscale and dark grayscale until both RGB High and RGB Low are balanced and DeltaE is under 3.




Selecting Points:

- **30% and 80%:** Use these levels if you only have access to a two point grayscale adjustment
- **30% and 100%:** Use these levels if you will be completing a multipoint adjustment afterwards and do not have access to a Peak White pattern.
- **30% and Peak White:** Use these levels if your display does not clip and you will be completing a multipoint calibration and want the best possible results.

	30	100
RGB Triplet	82, 82, 82	235, 235, 235
Red index	82.0000	235.0000
Green index	82.0000	235.0000
Blue index	82.0000	235.0000
X	5.6020	78.2089
Y cd/m²	5.9194	80.8831
Z	6.4321	88.7290
Xn 0-1	0.0280	0.3910
Yn 0-1	0.0296	0.4044
Zn 0-1	0.0322	0.4436
Stimulus Percent	0.3014	1.0000
RED Stim%:0-1	0.3014	1.0000
GRN Stim%:0-1	0.3014	1.0000
BLU Stim%:0-1	0.3014	1.0000




Multi-Point Grayscale



100

CCT 6364 6503 Target
 Gamma 5.43 2.2 Target
 dE ICTcp 0.89 / 44.19 w/ Lumin Error
 Read → Y cd/m² 80.88313 X 0.3156 Y 0.3264
 Target → 200 0.3127 0.329
 DDC 2 Point 30,100% Triplet 235, 235, 235



CalMAN 2018 CalMAN Home

Back Next

IM-Pt

HOME

Prepare

Session Setup

PreCal Read

Calibrate

IM-Pt

CMS

Sat

LUT

Lum

CCK

PostCal Read

Analyze

Post

Final Check

2-Pnt

IM-Pt

Notes

Back Next

2-Point Grayscale Calibration

Display Controls

Backlight 20

Brightness 2

Contrast 41

Sharpness 0

Color 24

Tint (G/R) -4

Color Tone Warm2

R-Gain 0

G-Gain 0

B-Gain -5





R-Offset 0

G-Offset -4

B-Offset 6

Gamma 2

HDMI Black Level Low



100

CCT 6364 6503 Target


Gamma 5.43 2.2 Target

dE ICTcp 0.89 / 44.19 w/ Lumin Error

Read → Y cd/m² 80.88313 X 0.3156 Y 0.3264

Target → 200 0.3127 0.329

DDC 2 Point 30,100% Triplet 235, 235, 235



CAL

Gray

2-Pnt

Back

Next

IM-Pt

HOME

Prepare

Session Setup

PreCal Read

Calibrate

IM-P

CMS

Sat

LUT

Lum

CCK

PostCal Read

Analyze

Post

Final Check


2-Pnt


IM-Pt

Notes

Back

Next





Multi-Point Grayscale Calibration

CCT

EOTF

Luminance

← Chart Mode

Comparator

2-Pt Grayscale

X Datagrid

Click grid to select it then
click Configure to select data

Configure

	7	10.5	15.5	19.6	24.7	29.7	35	39.7	44.7	49.8	55	60.3	65	70	75.3	81
RGB Triplet	31, 31, 31	39, 39, 39	50, 50, 50	59, 59, 59	70, 70, 70	81, 81, 81	93, 93, 93	103, 103, 103	114, 114, 114	125, 125, 125	136, 136, 136	148, 148, 148	158, 158, 158	169, 169, 169	181, 181, 181	193, 193, 193
Target Y cd/m ²	0.2900	0.7277	1.6981	2.8311	4.6531	6.9769	10.1064	13.2032	17.1367	21.6355	26.7115	32.9204	38.6392	45.5110	53.7123	62.6598
Y cd/m ²	0.5134	0.9155	1.6907	2.5970	3.9284	5.7230	8.0296	10.3271	13.2350	16.6965	20.6841	25.7408	30.3137	35.5389	42.1846	49.5516
Target x:CIE31	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127
x: CIE31	0.3142	0.3138	0.3126	0.3120	0.3114	0.3128	0.3143	0.3114	0.3115	0.3140	0.3118	0.3109	0.3115	0.3117	0.3141	0.3115
Target y:CIE31	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290
y: CIE31	0.3272	0.3272	0.3293	0.3302	0.3283	0.3317	0.3283	0.3280	0.3263	0.3282	0.3292	0.3311	0.3291	0.3278	0.3284	0.3283
Target CCT	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440
CCT	6435.0000	6455.0000	6510.0000	6532.0000	6579.0000	6481.0000	6419.0000	6584.0000	6589.0000	6440.0000	6553.0000	6588.0000	6571.0000	6566.0000	6430.0000	6577.0000

CAL

Adjust

M-Pnt

Back

Next

↑ 2-Pt

HOME

Prepare

Session

Setup

PreCal

Read

Calibrate

↑ 2-Pt

↓ CMS

↓ Sat

↓ LUT

↓ Lum

↓ CCK

PostCal

Read

Analyze

↓ Post

Final

Check


M-Pnt

↑ 2-Pt

Notes

Back

Next




CalMAN

Gamut Saturation



Gamut Saturation Calibration

DeltaE ICTcP w/ Luminance Error



Datagrid

Summary
 DeltaE w/Lum Err ↓
 Avg 0.37 / 9.92
 Max 1.27 / 11.08
 Delta L
 Avg 5.845
 Max 7.347
 Delta H
 Avg 0.445
 Max 1.411
 Delta C
 Avg 0.7166
 Max 1.871
 Black 0
 White 82.18





	Red	Green	Blue
Red	29	22	13
Green	45	39	23
Blue	22	23	34
Cyan	49	53	61
Magenta	4	24	55
Yellow	49	56	18

Reset CMS



Gamut Luminance Relative



Display Slot CAL-DAY
 Sweep Level BT.709 25% Sweeps


CAL Satur

Back Next

HOME Prepare Session Setup PreCal Read Calibrate I Gry I CMS I LUT I Lum I CCK PostCal Read Analyze J Post Final Check Satur

Notes

Back Next



Gamut Saturation Calibration

Datagrid

Configure

Click datagrid outside bottom right corner to select it then click Configure to select data

	25%	50%	75%	100%
RGB Triplet	180, 123, 123	180, 90, 90	180, 64, 64	180, 16, 16
Target Y cd/m ²	27.6279	18.5654	14.1040	11.2709
Y cd/m ²	21.5292	14.8746	11.3821	9.0538
Target x:CIE31	0.3937	0.4764	0.5563	0.6400
x: CIE31	0.3941	0.4738	0.5491	0.6368
Target y:CIE31	0.3293	0.3295	0.3297	0.3300
y: CIE31	0.3300	0.3328	0.3293	0.3298
Target CCT	3210.0466	1845.3325	1962.9459	3096.5526
CCT	3209.0000	1886.0000	1911.0000	3047.0000

?

CAL
Satur

Back

Next

HOME

Prepare

Session
SetupPreCal
Read

Calibrate

I Gry

I CMS

I LUT

I Lum

I CCK


PostCal
Read

Analyze

J Post




Final
Check

Satur






■ Datagrid



	Red	Green	Blue
Red	29	22	13
Green	45	39	23
Blue	22	23	34
Cyan	49	53	61
Magenta	4	24	55
Yellow	49	56	18

Reset CMS





Y Luminance Delta C, H, L

Gamut Lum Abs

Gamut Lum Rel

RGB Balance

← Chart Mode



Ramp Levels

4 Point 25% step 25-100%


Display
Slot


CAL-DAY

Notes

Back

Next





CalMAN

Simulated Meter
Simulated

Source

Direct Display Control

Color Checker Assessment Data

Color Notes

Post-Cal Notes

	White	Gray 80	Gray 65	Gray 50	Gray 35	Dark Skin	Light Skin	Blue Sky	Foliage	Blue Flower	Bluish Green	Orange	Purplish Blue	Moderate Red	Purple	Yellow G
RGB Triplet	235, 235, 235	213, 213, 213	196, 196, 196	176, 176, 176	152, 152, 152	115, 86, 73	182, 145, 128	97, 121, 150	93, 108, 73	128, 126, 167	101, 178, 161	202, 119, 51	80, 95, 156	182, 88, 99	95, 69, 108	152, 176, 152
Target Y cd/m²	100.0000	79.2590	65.0145	50.2050	35.1480	9.9716	35.6179	19.1127	13.1987	23.8604	42.4852	28.6553	11.7829	18.6747	6.5450	43.7286
Y cd/m²	81.8139	63.8600	51.6044	39.6294	27.6990	7.9403	27.9251	14.9784	10.4486	18.6678	33.8266	22.6482	9.3353	14.8345	5.3204	34.5484
Target x:CIE31	0.3127	0.3127	0.3127	0.3127	0.3127	0.4057	0.3778	0.2491	0.3415	0.2687	0.2615	0.5141	0.2150	0.4635	0.2884	0.3773
x: CIE31	0.3121	0.3122	0.3117	0.3135	0.3130	0.4022	0.3777	0.2482	0.3363	0.2661	0.2629	0.5149	0.2163	0.4627	0.2903	0.3731
Target y:CIE31	0.3290	0.3290	0.3290	0.3290	0.3290	0.3643	0.3561	0.2656	0.4314	0.2530	0.3593	0.4095	0.1896	0.3123	0.2170	0.4951
y: CIE31	0.3290	0.3298	0.3293	0.3286	0.3302	0.3615	0.3573	0.2663	0.4288	0.2538	0.3626	0.4041	0.1905	0.3137	0.2214	0.4949
Target CCT	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	3278.9495	3931.9347	17004.8230	5258.4868	15500.1515	8916.1635	2106.8573	16532072.9677	1816.3588	23330.5377	4592.49
CCT	6535.0000	6524.0000	6557.0000	6461.0000	6479.0000	3334.0000	3943.0000	17020.0000	5396.0000	15905.0000	8766.0000	2064.0000	8642804.0000	1830.0000	19159.0000	4670.00
dE ICtCp	9.6094	10.1717	10.6916	10.6687	10.3996	8.5072	10.6424	9.9461	9.0707	10.3420	10.1518	10.0820	8.9910	9.4616	7.4378	10.5473
dE ICtCp LuminanceCompensated	0.1299	0.1929	0.2327	0.2101	0.1403	0.4799	0.1787	0.2370	0.7019	0.6885	0.3597	1.1183	0.2972	0.4030	0.5085	0.6536
Red PQ Diff	-0.0207	-0.0222	-0.0235	-0.0211	-0.0220	0.0264	0.0162	-0.0650	-0.0431	-0.0287	-0.1248	0.0631	-0.0582	0.0746	0.0205	-0.0452
Green PQ Diff	-0.0198	-0.0208	-0.0219	-0.0226	-0.0214	-0.0321	-0.0333	-0.0167	-0.0085	-0.0268	-0.0030	-0.0578	-0.0262	-0.0782	-0.0401	-0.0085
Blue PQ Diff	-0.0199	-0.0215	-0.0221	-0.0222	-0.0224	-0.0612	-0.0613	0.0289	-0.0835	0.0335	-0.0279	-0.2073	0.0783	-0.0566	0.0450	-0.1929
dE94 L LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
dE94 C LuminanceCompensated	0.3247	0.6082	0.5482	0.4977	0.4468	0.6884	0.0110	0.0639	0.4020	0.4842	0.4847	0.5819	0.3354	0.5315	1.3943	0.4121
dE94 H LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	0.4998	0.4706	0.5238	1.1227	1.1726	0.9515	2.2495	0.1790	0.4365	0.1337	1.4669
Signed dE94 L LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Signed dE94 C LuminanceCompensated	0.3247	0.6082	0.5482	0.4977	0.4468	-0.6884	-0.0110	-0.0639	-0.4020	-0.4842	0.4847	-0.5819	-0.3354	-0.5315	-1.3943	-0.4121
Signed dE94 H LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	-0.4998	0.4706	-0.5238	1.1227	-1.1726	-0.9515	-2.2495	0.1790	0.4365	0.1337	1.4669

CalMAN CChkr

Asmt

HOME

Prepare

Calibrate

Asmt

Analyze

DTA

Asmt

Notes

≡ Color Checker Assessment Data Slim 1 ≡

Color
NotesPost-Cal
Notes

CAL

	White	Gray 80	Gray 65	Gray 50	Gray 35	Dark Skin	Light Skin	Blue Sky	Foliage	Blue Flower	Bluish Green	Orange	Purplish Blue	Moderate Red	Purple	Yellow Green
RGB Triplet	235, 235, 235	213, 213, 213	196, 196, 196	176, 176, 176	152, 152, 152	115, 86, 73	182, 145, 128	97, 121, 150	93, 108, 73	128, 126, 167	101, 178, 161	202, 119, 51	80, 95, 156	182, 88, 99	95, 69, 108	152, 176, 71
Target Y cd/m ²	100.0000	79.2590	65.0145	50.2050	35.1480	9.9716	35.6179	19.1127	13.1987	23.8604	42.4852	28.6553	11.7829	18.6747	6.5450	43.7286
Y cd/m ²	81.8139	63.8600	51.6044	39.6294	27.6990	7.9403	27.9251	14.9784	10.4486	18.6678	33.8266	22.6482	9.3353	14.8345	5.3204	34.5484
Target x:CIE31	0.3127	0.3127	0.3127	0.3127	0.3127	0.4057	0.3778	0.2491	0.3415	0.2687	0.2615	0.5141	0.2150	0.4635	0.2884	0.3773
x: CIE31	0.3121	0.3122	0.3117	0.3135	0.3130	0.4022	0.3777	0.2482	0.3363	0.2661	0.2629	0.5149	0.2163	0.4627	0.2903	0.3731
Target y:CIE31	0.3290	0.3290	0.3290	0.3290	0.3290	0.3643	0.3561	0.2656	0.4314	0.2530	0.3593	0.4095	0.1896	0.3123	0.2170	0.4951
y: CIE31	0.3290	0.3298	0.3293	0.3286	0.3302	0.3615	0.3573	0.2663	0.4288	0.2538	0.3626	0.4041	0.1905	0.3137	0.2214	0.4949
Target CCT	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	3278.9495	3931.9347	17004.8230	5258.4868	15500.1515	8916.1635	2106.8573	16532072.9677	1816.3588	23330.5377	4592.4945
CCT	6535.0000	6524.0000	6557.0000	6461.0000	6479.0000	3334.0000	3943.0000	17020.0000	5396.0000	15905.0000	8766.0000	2064.0000	8642804.0000	1830.0000	19159.0000	4670.0000
dE ICtCp	9.6094	10.1717	10.6916	10.6687	10.3996	8.5072	10.6424	9.9461	9.0707	10.3420	10.1518	10.0820	8.9910	9.4616	7.4378	10.5473
dE ICtCp LuminanceCompensated	0.1299	0.1929	0.2327	0.2101	0.1403	0.4799	0.1787	0.2370	0.7019	0.6885	0.3597	1.1183	0.2972	0.4030	0.5085	0.6536

Asmt

HOME

Prepare

Calibrate

Asmt

Data2

Analyze

DTA

Asmt

Datagrid 2

Notes

Color Checker Assessment Data Slim 2

Color Notes

Post-Cal Notes

	White	Gray 80	Gray 65	Gray 50	Gray 35	Dark Skin	Light Skin	Blue Sky	Foliage	Blue Flower	Bluish Green	Orange	Purplish Blue	Moderate Red	Purple	Yellow Green	Orange Yellow	Blue	Green	Red	Yellow	Ma
Red PQ Diff	-0.0207	-0.0222	-0.0235	-0.0211	-0.0220	0.0264	0.0162	-0.0650	-0.0431	-0.0287	-0.1248	0.0631	-0.0582	0.0746	0.0205	-0.0452	0.0360	-0.0567	-0.1204	0.0931	0.0143	0.0
Green PQ Diff	-0.0198	-0.0208	-0.0219	-0.0226	-0.0214	-0.0321	-0.0333	-0.0167	-0.0085	-0.0268	-0.0030	-0.0578	-0.0262	-0.0782	-0.0401	-0.0085	-0.0364	-0.0316	0.0000	-0.1045	-0.0245	-0.0
Blue PQ Diff	-0.0199	-0.0215	-0.0221	-0.0222	-0.0224	-0.0612	-0.0613	0.0289	-0.0835	0.0335	-0.0279	-0.2073	0.0783	-0.0566	0.0450	-0.1929	-0.2330	0.1119	-0.1216	-0.0898	-0.3012	0.0
ΔE 1994 L*:±	-7.5074	-7.4585	-7.4475	-6.9901	-6.2479	-3.9331	-6.4060	-5.2143	-4.4253	-5.6514	-6.3794	-5.7682	-4.2469	-4.8978	-3.1193	-6.6511	-6.4352	-2.6394	-5.7331	-3.7400	-6.9700	-5.0
ΔE 1994 Sat:±	0.3247	0.6082	0.5482	0.4977	0.4468	-2.1433	-1.6726	-1.7606	-2.3931	-2.6544	-1.8582	-5.6204	-3.6285	-4.0854	-3.5814	-5.2374	-6.3819	-7.0764	-6.1094	-7.2286	-6.4182	-3.0
ΔE 1994 Hue:±	0.0000	0.0000	0.0000	0.0000	0.0000	-0.5191	0.4901	-0.5456	1.1673	-1.2216	-0.9883	-2.3395	0.1861	0.4536	0.1384	1.5257	-0.1405	-0.7258	0.0529	0.2784	-0.8165	0.6
Signed dE94 L LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0
Signed dE94 C LuminanceCompensated	0.3247	0.6082	0.5482	0.4977	0.4468	-0.6884	-0.0110	-0.0639	-0.4020	-0.4842	0.4847	-0.5819	-0.3354	-0.5315	-1.3943	-0.4121	-1.3235	-3.6982	-1.7918	-3.3155	-0.7557	0.6
Signed dE94 H LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	-0.4998	0.4706	-0.5238	1.1227	-1.1726	-0.9515	-2.2495	0.1790	0.4365	0.1337	1.4669	-0.1353	-0.7045	0.0507	0.2690	-0.7868	0.6

Asmt

HOME

Prepare

Calibrate

Asmt

Data1

Analyze

DTA

Asmt

3D Color Cube LUT Calibration - Full
DeltaE ICTCp w/Luminance Error

Go to Minimal 3D LUT

Datagrid

Points 195

Virtual LUT

CAL
3dLUT
Full

Back

Next

HOME

Prepare

Session
SetupPreCal
Read

Calibrate

I Gry

I CMS

I Sat

I Lum

I CCK

PostCal
Read


Analyze

↓

f Chrts

Final
Check

3dLUT





Summary

Delta C
2.24 Avg 4.74 MaxDelta H
0.83 Avg 2.13 MaxDelta L
2.86 Avg 4.61 MaxDelta E
Avg 3.11 / 8.6
Max 12.32 / 14.82
w/Luminance Error

RGB Balance

dE ICTCp

Triplet
235, 16, 16Y 17.29603
Tgt 21.26567
x 0.63765
Tgt 0.64
y 0.33047
Tgt 0.33
dC -8.04
dH -0.37
dL -4.61
dE 0.61
/ 8.81100 White
0.097695 BlackdE Avg 3.11 / 8.6
dE Max 12.32 / 14.82

X u'v' CIE

X Color Bars

X Big Comparator

100 0 0 dE 0.61 / 8.81

Red

Green

Blue

Cyan

Magenta

Yellow

White

Ramp

Inner Data Points

Luminance Level Points



Notes

Back

Next

Summary

Points 195

Black 0.098826

White 100

dE Avg 3.17 / 7.99

dE Max 12.96 / 17.07

dE ICtCp

dE @ 0 0 100 0.42

w/ Luminance Error 7.59

dL -3.05 dH -0.31 dC -9.88

RGB Balance

R 1.5 G 3.3 B -23.8



Red

Green

Blue

Cyan

Magenta

Yellow

White

Read Cube Ramp

Go to [Charts](#)

View charts in the Analysis section

Luminance Level Points

15 Points per side, SMPTE (0-100)

Inner Data Points

Display Slot

Selected LUT


Post-Calibration Readings

7/28/2018 Calibration

Gamma Breakout Tot 2.86 Contrast 827

Black 0.099564 White 82.33 cd/m²


95



1 Grayscale

Detail Charts



21 Point 5% step 0-100%

Avg 0.33 / 9.03
Max 0.78 / 14.61

2 Saturation Sweeps

Detail Charts

BT.709 25% Sweeps

Avg 0.64 / 9.32
Max 1.81 / 11.17


4 Color Checker

Detail Charts

3 Gamut Luminance

Detail Charts

4 Point 25% step 25-100%

Avg 0.89 / 8.19
Max 4.62 / 11.05

Cal Day 300 nits

Post-Cal Readings

Use calibration layout tabs for
additional detailed readings

Contrast

Brightness

Backlight

TV Gamma

Color

Tint

Red

Green

Blue

Gain

Cut

Notes

Display Slot

Custom

Use [...] mid-screen or below to read all series
or select one from the individual series aboveCAL
PstCal
Read

Back

Next

PreCal

Read

HOME

Prepare

Session

Setup

PreCal

Read

Calibrate

Gry

CMS

Sat

LUT

Lum

CCK

PreCal

Read

Analyze

Gry

Sat

Lum

CCK

LUT

Final

Check

PstCal

Notes

Back

Next

Post-Cal Multi-Point Grayscale Detail

Comparator


DeltaE ICTCp w/ Luminance Error Contrast 827 95 dE 10.34 9.03 Avg 14.61 Max





DeltaE ICTCp Post-Cal Readings 95 dE 0.14 0.33 Avg 0.78 Max



RGB Balance




Gamma Target 2.2 6.42 2.86 Total




POST-CAL

95


White 82.3
Black 0.09956





Luminance cd/m² Target 89.3011 71.8327



EOTF



CCT 6523 6538 Avg




- ANL
- PstCal
- Gray
- Back
- Next
- PreCal
- # Data
- HOME
- Prepare
- Session Setup
- PreCal Read
- Calibrate
- I Gry
- PostCal Read
- Analyze
- PreCal
- f Sat
- f Lum
- f CCK
- f LUT
- Final Check
- PstCal
- Gray
- Notes

Pre-Cal # Datagrid

Back Next

Post-Cal Saturation Sweeps Detail




Comparator



Avg 9.32 Max 11.17 Post-Cal Readings dE w/ Lumin Error 10.42




Avg 0.64 Max 1.806 DeltaE ICtCp 0.37






Post-Cal

100%



Post-Cal








Avg 8.19 Max 11.05 dE w/ Lumin Error 9.6



Avg 0.89 Max 4.62 DeltaE IctCp 0.32



Post-Cal Post-Cal Readings 100




Post-Cal



ANL
PstCal
Lumi
Back
Next
PreCal
Data
HOME
Prepare
Session Setup
PreCal Read
Calibrate
Lum
PostCal Read
Analyze
Gry
Sat
PreCal
Cck
LUT
Final Check
PstCal
Lumi
Notes
Pre-Cal # Datagrid
Back Next






3D Color Cube LUT Full Calibration Detail 1

dE ICtCp 0.53 / 8.11 Avg 2.94 / 8.44 Max 11.74 / 14.48 Delta L -4.25 Avg -2.58 Max 4.47 Luminance 17.58216



Red Green Blue White
Cyan Magenta Yellow Charts 2



Navigation and control panel on the right side of the interface. It includes buttons for 'Back', 'Next', 'Calib', 'HOME', 'Prepare', 'Session Setup', 'PreCal Read', 'Calibrate', 'PostCal Read', 'Analyze', 'Gry', 'Sat', 'Lum', 'CCk', 'Final Check', and 'CAL'. There are also checkboxes for 'Calib', 'chrts2', and 'Final Check'.


CalMAN

DeltaE DeltaH DeltaC



Simulated Meter Simulated Source Direct Display Control

3D Color Cube LUT Full Calibration Detail 2

dE ICtCp 0.53 / 8.11 Avg 2.94 / 8.44 Max 11.74 / 14.48 Delta H -0.25 Avg 0.9 Max 2.02 Delta C 7.35 Avg 5.82 Max 8.3



Red Green Blue White
Cyan Magenta Yellow Charts 1



ANL 3dLUT Detail
Back Next
Calib
HOME
Prepare Session Setup PreCal Read Calibrate
Calib
PostCal Read Analyze
Gry Sat Lum Ck
Calib
chrts1
Final Check
CAL
Calib

Datagrid Notes
Back Next



CalMAN

DeltaE DeltaL Luminance


Simulated Meter Simulated Source Direct Display Control

3D Color Cube LUT Minimal Calibration - Charts1
 dE lCtCp 0.42 Avg 3.17 Max 12.96
 / 7.59 / 7.99 / 17.07

Delta L -3.05 Avg -2 Max 4.36 Luminance 5.93696



Red Green Blue White
 Cyan Magenta Yellow Charts 2



0 0 Ramp 000 007.3 0014.6 0022 0029 0036.5 0044 0051 0058.4 0065.8 0073 0080.4 0087.7 0095 00100

Datagrid Notes

Back Next

Session Final Check 7/28/2018 Calibration

AV Mode - Cal Day 300 nits

Contrast Verification

Data Points: select Clipping or Clipping with Peak White: Clipping with Peak White


- ① Adjust the Backlight, Brightness and Contrast controls to optimize the white level so it doesn't clip any of the primaries.

Gamma Level Verification

Data Points: select a full set of grayscale points, e.g. 11: Clipping with Peak White

- ② Check / adjust the gamma level across the full grayscale. Use the Backlight, Brightness, Contrast and Gamma controls to make this adjustment.

Luminance



~~107~~
Gamma -0.64
27.96599 cd/m²

Post-Calibration Summary


Grayscale dE Avg 0 Saturation dE Avg 0
Max 0 Max 0

Luminance dE Avg 0 Color Checker dE Avg 0
Max 0 Max 0

Color Cube LUT dE Avg 8.44 Full Gamma Target 2.2
Total 2.2
Use Minimal layout data Max 14.48 CCT Target 6503
Avg 0

White 100 cd/m² Black 0 Cntr Ratio 0

Gamma Log/Log



Post-Calibration Notes

Notes

Save

Contrast
Brightness
Backlight

TV Gamma
Color
Tint

Red Green Blue
Gain
Cut

Notes

Back

Save

CalMAN

Grayscale Datagrids +

Simulated Meter
Simulated

Source

Direct Display Control

?

?

Pre-Cal Multi-Point Grayscale Data

Pre-Cal

	0	5	10	15	20	25	30	35	40	45	50	55	60	65	70	75	80	85	90
RGB Triplet	16, 16, 16	27, 27, 27	38, 38, 38	49, 49, 49	60, 60, 60	71, 71, 71	82, 82, 82	93, 93, 93	104, 104, 104	115, 115, 115	126, 126, 126	136, 136, 136	147, 147, 147	158, 158, 158	169, 169, 169	180, 180, 180	191, 191, 191	202, 202, 202	213, 213, 213
Target Y cd/m ²	0.0001	0.1497	0.6611	1.5914	2.9765	4.8433	7.2137	10.1064	13.5377	17.5222	22.0729	26.7115	32.3759	38.6392	45.5110	53.0005	61.1162	69.8665	79.2500
Y cd/m ²	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Target x:CIE31	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127
x: CIE31	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Target y:CIE31	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290
y: CIE31	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Target CCT	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440
CCT	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000

Post-Cal Multi-Point Grayscale Data

Post-Cal

	0	5	10	15	20	25	30	35	40	45	50	55	60	65	70	75	80	85	90
RGB Triplet	16, 16, 16	27, 27, 27	38, 38, 38	49, 49, 49	60, 60, 60	71, 71, 71	82, 82, 82	93, 93, 93	104, 104, 104	115, 115, 115	126, 126, 126	136, 136, 136	147, 147, 147	158, 158, 158	169, 169, 169	180, 180, 180	191, 191, 191	202, 202, 202	213, 213, 213
Target Y cd/m ²	0.0001	0.1497	0.6611	1.5914	2.9765	4.8433	7.2137	10.1064	13.5377	17.5222	22.0729	26.7115	32.3759	38.6392	45.5110	53.0005	61.1162	69.8665	79.2500
Y cd/m ²	0.0995	0.3629	0.8548	1.6328	2.6905	4.0828	5.8819	8.0148	10.5787	13.6639	17.0725	20.9271	25.1011	30.3738	36.0370	42.0427	48.2878	56.0356	63.5800
Target x:CIE31	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127	0.3127
x: CIE31	0.3129	0.3143	0.3140	0.3110	0.3101	0.3150	0.3137	0.3126	0.3137	0.3136	0.3154	0.3121	0.3147	0.3100	0.3092	0.3126	0.3121	0.3124	0.3133
Target y:CIE31	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290	0.3290
y: CIE31	0.3300	0.3287	0.3265	0.3301	0.3297	0.3283	0.3300	0.3297	0.3273	0.3304	0.3281	0.3316	0.3270	0.3309	0.3305	0.3299	0.3289	0.3295	0.3280
Target CCT	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440	6503.4440
CCT	6484.0000	6420.0000	6449.0000	6591.0000	6644.0000	6384.0000	6441.0000	6504.0000	6459.0000	6446.0000	6364.0000	6517.0000	6409.0000	6639.0000	6683.0000	6501.0000	6540.0000	6518.0000	6458.0000

Click Change Selection then right-click on either datagrid chart (ESCAPE the context menu) to show possible selections

Change Selection

Pre-Cal

Post-Cal

Back

Next

ANL

Back

Next

PreCal

PostCal

HOME

Prepare

PreCal Read

Calibrate

I Gry

PostCal Read

Datagrid

Sat

Lum

Cck

Final Check

DTA

Notes

≡ Pre-Cal Saturation Sweeps Data ≡

	25%	50%	75%	100%
RGB Triplet	180, 123, 123	180, 90, 90	180, 64, 64	180, 16, 16
Target x:CIE31	0.3937	0.4764	0.5563	0.6400
x: CIE31	0.0000	0.0000	0.0000	0.0000
Target y:CIE31	0.3293	0.3295	0.3297	0.3300
y: CIE31	0.0000	0.0000	0.0000	0.0000
Target Y	27.6279	18.5654	14.1040	11.2709
Y	0.0000	0.0000	0.0000	0.0000
Gamma Point: Flat	0.0000	0.0000	0.0000	0.0000
ΔE 2000	0.0000	0.0000	0.0000	0.0000
dE2000 LuminanceCompensated	0.0000	0.0000	0.0000	0.0000
ΔE 1994 L*:±	0.0000	0.0000	0.0000	0.0000
ΔE 1994 Sat:±	0.0000	0.0000	0.0000	0.0000
ΔE 1994 Hue:±	0.0000	0.0000	0.0000	0.0000
Signed dE94 L LuminanceCompensated	0.0000	0.0000	0.0000	0.0000
Signed dE94 C LuminanceCompensated	0.0000	0.0000	0.0000	0.0000
Signed dE94 H LuminanceCompensated	0.0000	0.0000	0.0000	0.0000

≡ Post-Cal Saturation Sweeps Data ≡

	25%	50%	75%	100%
RGB Triplet	126, 86, 86	147, 75, 75	165, 60, 60	180, 16, 16
Target x:CIE31	0.3991	0.4767	0.5549	0.6400
x: CIE31	0.3934	0.4711	0.5430	0.6354
Target y:CIE31	0.3293	0.3295	0.3297	0.3300
y: CIE31	0.3300	0.3286	0.3301	0.3311
Target Y	11.1535	11.3303	11.4753	11.2709
Y	8.8760	9.0665	9.2385	8.9706
Gamma Point: Flat	3.5302	4.6921	6.2182	8.3958
ΔE 2000	3.9044	3.7531	3.9337	3.9140
dE2000 LuminanceCompensated	0.8394	0.5055	0.9007	0.4218
ΔE 1994 L*:±	-4.0935	-4.0192	-3.9301	-4.1055
ΔE 1994 Sat:±	-2.9961	-3.9724	-6.9381	-7.8976
ΔE 1994 Hue:±	0.1326	-0.4761	-0.6553	-0.5088
Signed dE94 L LuminanceCompensated	0.0000	0.0000	0.0000	0.0000
Signed dE94 C LuminanceCompensated	-1.3819	-1.0686	-2.7921	-1.6211
Signed dE94 H LuminanceCompensated	0.1277	-0.4587	-0.6321	-0.3985

Pre-Cal

Click Change Selection then right-click on either datagrid chart (ESCAPE the context menu) to show possible selections

Post-Cal

25%

50%

75%

100%

Change Selection

25%

50%

75%

100%

Pre-Cal

Post-Cal

Back

Next

ANL

Back

Next

PreCal

PostCal

HOME

Prepare

PreCal
Read

Calibrate

I Sat

PostCal
Read

Datagrid

Gry

Lum

CCK

Final
Check

DTA

Notes

Pre-Cal Color Checker Data

Pre-Cal

	White	Gray 80	Gray 65	Gray 50	Gray 35	Dark Skin	Light Skin	Blue Sky	Foliage	Blue Flower	Bluish Green	Orange	Purplish Blue	Moderate Red	Purple	Yellow Gre
RGB Triplet	235, 235, 235	213, 213, 213	196, 196, 196	176, 176, 176	152, 152, 152	115, 86, 73	182, 145, 128	97, 121, 150	93, 108, 73	128, 126, 167	101, 178, 161	202, 119, 51	80, 95, 156	182, 88, 99	95, 69, 108	152, 176,
Target x:CIE31	0.3127	0.3127	0.3127	0.3127	0.3127	0.4057	0.3778	0.2491	0.3415	0.2687	0.2615	0.5141	0.2150	0.4635	0.2884	0.3773
x: CIE31	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Target y:CIE31	0.3290	0.3290	0.3290	0.3290	0.3290	0.3643	0.3561	0.2656	0.4314	0.2530	0.3593	0.4095	0.1896	0.3123	0.2170	0.4951
y: CIE31	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Target Y	100.0000	79.2590	65.0145	50.2050	35.1480	9.9716	35.6179	19.1127	13.1987	23.8604	42.4852	28.6553	11.7829	18.6747	6.5450	43.7286
Y	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Gamma Point: Flat	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
ΔE 2000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
dE2000 LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
ΔE 1994 L*:±	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
ΔE 1994 Sat:±	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
ΔE 1994 Hue:±	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000
Signed dE94 L LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000

Post-Cal Color Checker Data

Post-Cal

	White	Gray 80	Gray 65	Gray 50	Gray 35	Dark Skin	Light Skin	Blue Sky	Foliage	Blue Flower	Bluish Green	Orange	Purplish Blue	Moderate Red	Purple	Yellow Gre
RGB Triplet	235, 235, 235	213, 213, 213	196, 196, 196	176, 176, 176	152, 152, 152	115, 86, 73	182, 145, 128	97, 121, 150	93, 108, 73	128, 126, 167	101, 178, 161	202, 119, 51	80, 95, 156	182, 88, 99	95, 69, 108	152, 176,
Target x:CIE31	0.3127	0.3127	0.3127	0.3127	0.3127	0.4057	0.3778	0.2491	0.3415	0.2687	0.2615	0.5141	0.2150	0.4635	0.2884	0.3773
x: CIE31	0.3139	0.3134	0.3123	0.3120	0.3151	0.4025	0.3814	0.2508	0.3384	0.2670	0.2610	0.5141	0.2164	0.4650	0.2896	0.3723
Target y:CIE31	0.3290	0.3290	0.3290	0.3290	0.3290	0.3643	0.3561	0.2656	0.4314	0.2530	0.3593	0.4095	0.1896	0.3123	0.2170	0.4951
y: CIE31	0.3282	0.3269	0.3278	0.3281	0.3267	0.3615	0.3550	0.2662	0.4245	0.2531	0.3579	0.4049	0.1911	0.3105	0.2214	0.4960
Target Y	100.0000	79.2590	65.0145	50.2050	35.1480	9.9716	35.6179	19.1127	13.1987	23.8604	42.4852	28.6553	11.7829	18.6747	6.5450	43.7286
Y	81.4120	63.5920	51.4250	39.3078	27.2482	7.9312	27.8845	15.0129	10.3310	18.7117	33.1915	22.7612	9.3286	14.7228	5.3292	34.5857
Gamma Point: Flat	2.7023	4.3221	3.4097	2.9860	2.7378	3.2036	4.6356	3.8760	2.6261	4.5300	3.6755	9.1609	5.3273	6.9613	3.3933	3.3970
ΔE 2000	4.7665	5.2138	5.2253	5.4332	6.0900	3.5089	5.5155	5.2371	4.4645	5.5972	5.6067	5.4869	3.9182	5.0723	2.8345	5.4539
dE2000 LuminanceCompensated	1.4206	1.8543	0.6104	0.3763	2.2516	0.5576	1.1445	0.4154	0.7707	0.6543	0.2953	1.2193	0.2125	0.3800	0.6510	0.9850
ΔE 1994 L*:±	-7.6853	-7.5985	-7.5555	-7.2213	-6.6604	-3.9521	-6.4427	-5.1670	-4.6311	-5.5996	-6.8884	-5.6507	-4.2595	-5.0523	-3.0952	-6.6219
ΔE 1994 Sat:±	0.9800	1.3610	0.5186	0.3676	1.5963	-2.0930	-0.5737	-2.0131	-3.5686	-2.2937	-2.7438	-5.6945	-3.8803	-2.8781	-3.6724	-4.8972
ΔE 1994 Hue:±	0.0000	0.0000	0.0000	0.0000	0.0000	-0.5205	-0.9799	0.3763	0.4313	-0.7036	0.4289	-1.9552	0.0727	-0.4794	-0.0374	1.9343
Signed dE94 L LuminanceCompensated	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000	0.0000

Click Change Selection then right-click on either datagrid chart (ESCAPE the context menu) to show possible selections

Change Selection



Pre-Cal

Post-Cal

Back

Next